

Biometric Technology Provider

How to register the fingerprint by FOH02 in Alpeta

ACCESS CONTROL
TIME ATTENDANCE
MANAGEMENT
SOLUTIONS








How to register the fingerprint by FOH02 in Alpeta

- ① From the main screen, select [**User**] > [**Add**] to add the user.
Enter [**User Name**] and [**User ID**] and then select **FP** as authentication type.

User Info

UBio Alpeta



User Name
Claire ✓




User ID
00000001 ✓

Unique ID

Duplicate Check

Terminal List

Save ?

Basic	Auth	Access	Management	Etc
Auth Info	AND Auth	OR Auth		 Modify
		FP		
Privilege	Admin ▼			
Set Regulatory Period	<input type="radio"/> Used <input checked="" type="radio"/> Not Used			
Expiration Date	Regist Date	2020-04-23 	~	Expire Date 2020-04-23 






How to register the fingerprint by FOH02 in Alpeta

② Select [**Auth**] and [**Edit**] in FP data section.

User Info

UBio Alpeta



User Name

Claire

User ID

00000001

Unique ID

Duplicate Check

Terminal List

Save

BasicAuthAccessManagementEtc

Auth Level5

Fingerprint (1:N)OnOff

Face (1:N)OnOff

FP DataEdit

Face Data

Face Data (W)



PassWord

Card



How to register the fingerprint by FOH02 in Alpeta


- ③ Select [**Hamster**]. If it is the first time to register by FOH02, you should download the hamster control program. Please follow the link for “Download: Hamster Control Program”.






How to register the fingerprint by FOH02 in Alpeta




④ If the installation is completed, you can see the message “**Hamster Connection Success**”.



How to register the fingerprint by FOH02 in Alpeta





- ⑤ Select the finger to register and click [**Fingerprint regist**].
You can check the light of the hamster is flickering to register the fingerprint.





How to register the fingerprint by FOH02 in Alpeta

⑥ Place your finger twice on the sensor of FOH02 and select [**Enroll**] > [**Apply**] in order.





How to register the fingerprint by FOH02 in Alpeta

⑦ Select [**Save**] to save the user information.

User Info

UBio Alpeta

Terminal List Save

Basic	Auth	Access	Management	Etc
Auth Level	5			
Fingerprint (1:N)	<input checked="" type="checkbox"/> On <input type="checkbox"/> Off			
Face (1:N)	<input checked="" type="checkbox"/> On <input type="checkbox"/> Off			
FP Data	Edit			
Face Data				
Face Data (W)				
PassWord				
Card				

User Name: Claire ✓

User ID: 00000001 ✓

Unique ID: Duplicate Check



User Info

UBio Alpeta

Terminal List Save

Basic	Auth	Access	Management	Etc
Auth Level	5			
Fingerprint (1:N)	<input checked="" type="checkbox"/> On <input type="checkbox"/> Off			
Face (1:N)	<input checked="" type="checkbox"/> On <input type="checkbox"/> Off			
FP Data	Edit			
Face Data				
Face Data (W)				
PassWord				
Card				

User Name: Claire ✓

User ID: 00000001 ✓

Unique ID: Duplicate Check

Success

User Add

OK